

CentOS 7 – MariaDB 10.6

Version:	1.0.0
Created by:	cloudimg

Table of Contents

1.) Overview.....	1
2.) Access & Security.....	1
3.) System Requirements.....	2
4.) Connecting to the Instance.....	2
5.) On Startup.....	2
6.) Filesystem Configuration.....	3
7.) Server Components.....	3
8.) Scripts and Log Files.....	4
9.) Using System Components.....	4

1.) Overview

This document is provided as a user guide for the CentOS 7 – MariaDB 10.6 product offering on the Azure Marketplace. Please reach out to support@cloudimg.co.uk if any issues are encountered following this user guide for the chosen product offering.

2.) Access & Security



Registered
Technology
Partner

cloudimg
(+44) 02045382725
3rd Floor 86-90 Paul Street London EC2A 4NE
support@cloudimg.co.uk
<https://cloudimg.co.uk>

Please update the security group of the target instance to allow the below ports and protocols for access and connectivity.

Protocol	Type	Port	Description
SSH	TCP	22	SSH connectivity
Custom TCP	TCP	3306	MariaDB Database Listener Port for remote access

3.) System Requirements

The minimum system requirements for the chosen product offering can be found below

Minimum CPU	Minimum RAM	Required Disk Space
1	1 GB	20 GB

4.) Connecting to the Instance

Once launched in the Azure Virtual Machines Service, please connect to the instance via an SSH client using the **azureuser** with the key pair associated at launch. Once connected as the **azureuser**, you will be able to **sudo** to the **root** user by issuing the below command.

Switch to the root user

```
sudo su -
```

5.) On Startup

An OS package update script has been configured to run on boot to ensure the image is fully up to date at first use. You can disable this feature by removing the script from /stage/scripts/ and deleting the entry in crontab for the root user.

Disable the OS update script from running on reboot

```
rm -f /stage/scripts/initial_boot_update.sh  
crontab -e  
  
#DELETE THE BELOW LINE. SAVE AND EXIT THE FILE.  
@reboot /stage/scripts/initial_boot_update.sh
```



Registered
Technology
Partner

cloudimg
(+44) 02045382725
3rd Floor 86-90 Paul Street London EC2A 4NE
support@cloudimg.co.uk
<https://cloudimg.co.uk>

6.) Filesystem Configuration

Please see below for a screenshot of the server disk configuration and specific mount point mappings for software locations.

Filesystem	Size	Used	Avail	Use%	Mounted on
devtmpfs	472M	0	472M	0%	/dev
tmpfs	482M	0	482M	0%	/dev/shm
tmpfs	482M	6.5M	475M	2%	/run
tmpfs	482M	0	482M	0%	/sys/fs/cgroup
/dev/nvme0n1p2	38G	2.6G	33G	8%	/
/dev/nvme1n1	9.8G	161M	9.1G	2%	/var/lib/mysql
/dev/nvme0n1p1	2.0G	93M	1.7G	6%	/boot
tmpfs	97M	0	97M	0%	/run/user/1002

Mount Point	Description
/boot	Operating System Kernel files
/var/lib/mysql	MariaDB data directory

7.) Server Components

Please see below for a list of installed server components and their respective installation paths. The below versions are subject to change on initial boot based on the `initial_boot_update.sh` script finding new versions of the software in the systems package repositories.

Component	Version	Software Home
Cloud-Init	19.4	/etc/cloud
MariaDB 10.6	10.6.8	/etc/my.cnf
Azure CLI	2.53.1	/lib64/az



Registered
Technology
Partner

cloudimg
(+44) 02045382725
3rd Floor 86-90 Paul Street London EC2A 4NE
support@cloudimg.co.uk
<https://cloudimg.co.uk>

8.) Scripts and Log Files

The below table provides a breakdown of any scripts & log files created to enhance the useability of the chosen offering.

Script/Log	Path	Description
Initial_boot_update.sh	/stage/scripts	Update the Operating System with the latest updates available.
Initial_boot_update.log	/stage/scripts	Provides output for initial_boot_update.sh
mariadb_root_password.log	/stage/scripts	MariaDB root database password file

9.) Using System Components

Instructions can be found below for using each component of the server build mentioned in section 7 of this user guide document.

Azure CLI

Using Azure CLI – as any OS user.

```
az
```

Cloud-Init

Edit the /etc/cloud/cloud.cfg file to reflect your desired configuration. A link to the cloud-init official documentation can be found below for referencing best practise for your use case.

<https://cloudinit.readthedocs.io/en/latest/>

```
vi /etc/cloud/cloud.cfg
```

MariaDB



Registered
Technology
Partner

cloudimg
(+44) 02045382725
3rd Floor 86-90 Paul Street London EC2A 4NE
support@cloudimg.co.uk
<https://cloudimg.co.uk>

The MariaDB Database service has been configured to start on boot, please use the below commands to start, stop and check the status of the service.

```
#Check the MariaDB service is running  
service mariadb status  
  
#Stop the MariaDB service  
service mariadb stop  
  
#Start the MariaDB service  
service mariadb start
```

You can access the MariaDB database server as the root user by referring to the instructions in the /stage/scripts/mariadb_root_password.log file. The root database user has been disabled for remote login as per best practise and therefore only a local login from the server command line will be allowed for the root user.

```
mysql -u root -p  
  
#Enter the randomly generated password found in the /stage/scripts/mariadb_root_password.log  
file
```



Registered
Technology
Partner

cloudimg
(+44) 02045382725
3rd Floor 86-90 Paul Street London EC2A 4NE
support@cloudimg.co.uk
<https://cloudimg.co.uk>