

Rocky Linux 8 – NGINX

Version:	1.0.0
Created by:	cloudimg

Table of Contents

1.) Overview.....	1
2.) Access & Security.....	1
3.) System Requirements.....	2
4.) Connecting to the Instance.....	2
5.) On Startup.....	2
6.) Filesystem Configuration.....	3
7.) Server Components.....	3
8.) Scripts and Log Files.....	3
9.) Using System Components.....	4

1.) Overview

This document is provided as a user guide for the Rocky Linux 8 – NGINX product offering on the Azure Marketplace. Please reach out to support@cloudimg.co.uk if any issues are encountered following this user guide for the chosen product offering.

2.) Access & Security

Please update the security group of the target instance to allow the below ports and protocols for access and connectivity.



Registered
Technology
Partner

cloudimg
(+44) 02045382725
3rd Floor 86-90 Paul Street London EC2A 4NE
support@cloudimg.co.uk
<https://cloudimg.co.uk>

Protocol	Type	Port	Description
SSH	TCP	22	SSH connectivity
TCP	TCP	80	NGINX Front End

3.) System Requirements

The minimum system requirements for the chosen product offering can be found below

Minimum CPU	Minimum RAM	Required Disk Space
1	1 GB	20 GB

4.) Connecting to the Instance

Once launched in the Azure Virtual Machines Service, please connect to the instance via an SSH client using the **azureuser** with the key pair associated at launch. Once connected as the **azureuser**, you will be able to **sudo** to the **root** user by issuing the below command.

Switch to the root user

```
sudo su -
```

5.) On Startup

An OS package update script has been configured to run on boot to ensure the image is fully up to date at first use. You can disable this feature by removing the script from `/stage/scripts/` and deleting the entry in crontab for the root user.

Disable the OS update script from running on reboot

```
rm -f /stage/scripts/initial_boot_update.sh
crontab -e
#DELETE THE BELOW LINE. SAVE AND EXIT THE FILE.
@reboot /stage/scripts/initial_boot_update.sh
```



Registered
Technology
Partner

cloudimg
(+44) 02045382725
3rd Floor 86-90 Paul Street London EC2A 4NE
support@cloudimg.co.uk
<https://cloudimg.co.uk>

6.) Filesystem Configuration

Please see below for a screenshot of the server disk configuration and specific mount point mappings for software locations.

```
Filesystem      Size  Used Avail Use% Mounted on
devtmpfs        1.9G   0  1.9G   0% /dev
tmpfs           2.0G   0  2.0G   0% /dev/shm
tmpfs           2.0G  8.5M  1.9G   1% /run
tmpfs           2.0G   0  2.0G   0% /sys/fs/cgroup
/dev/nvme0n1p2  38G  2.6G  33G   8% /
/dev/nvme0n1p1  2.0G  148M  1.7G   9% /boot
tmpfs           391M   0  391M   0% /run/user/0
tmpfs           391M   0  391M   0% /run/user/1002
/dev/nvme1n1    9.8G  37M  9.2G   1% /usr/share/nginx
```

Mount Point	Description
/boot	Operating System Kernel files
/usr/share/nginx	NGINX Web Server Root

7.) Server Components

Please see below for a list of installed server components and their respective installation paths. The below versions are subject to change on initial boot based on the initial_boot_update.sh script finding new versions of the software in the systems package repositories.

Component	Version	Software Home
Cloud-Init	22.1-1	/etc/cloud
NGINX	1.20.1	/etc/nginx
Azure CLI	2.53.1	/lib64/az

8.) Scripts and Log Files



Registered
Technology
Partner

cloudimg
(+44) 02045382725
3rd Floor 86-90 Paul Street London EC2A 4NE
support@cloudimg.co.uk
<https://cloudimg.co.uk>

The below table provides a breakdown of any scripts & log files created to enhance the useability of the chosen offering.

Script/Log	Path	Description
Initial_boot_update.sh	/stage/scripts	Update the Operating System with the latest updates available.
Initial_boot_update.log	/stage/scripts	Provides output for initial_boot_update.sh

9.) Using System Components

Instructions can be found below for using each component of the server build mentioned in section 7 of this user guide document.

Azure CLI

Using Azure CLI - as any OS user.

```
az
```

Cloud-Init

Edit the /etc/cloud/cloud.cfg file to reflect your desired configuration. A link to the cloud-init official documentation can be found below for referencing best practise for your use case.

<https://cloudinit.readthedocs.io/en/latest/>

```
vi /etc/cloud/cloud.cfg
```

NGINX



Registered
Technology
Partner

cloudimg
(+44) 02045382725
3rd Floor 86-90 Paul Street London EC2A 4NE
support@cloudimg.co.uk
<https://cloudimg.co.uk>

The NGINX Server has been configured to start on boot, please use the below commands to start, stop and check the status of the service.

```
#Check the NGINX Server is running
systemctl status nginx

#Stop the NGINX Server
systemctl stop nginx

#Start the NGINX Server
systemctl start nginx
```

Once the NGINX Server status has started, you will be able to access the NGINX front end via the below URL exchanging the values between <> to match that of your own instance.

<PRIVATE/PUBLICIP>:80

Welcome to **nginx** on Red Hat Enterprise Linux!

This page is used to test the proper operation of the **nginx** HTTP server after it has been installed. If you can read this page, it means that the web server installed at this site is working properly.

Website Administrator

This is the default `index.html` page that is distributed with **nginx** on Red Hat Enterprise Linux. It is located in `/usr/share/nginx/html`.

You should now put your content in a location of your choice and edit the `root` configuration directive in the **nginx** configuration file `/etc/nginx/nginx.conf`.

For information on Red Hat Enterprise Linux, please visit the [Red Hat, Inc. website](#). The documentation for Red Hat Enterprise Linux is [available on the Red Hat, Inc. website](#).



Registered
Technology
Partner

cloudimg
(+44) 02045382725
3rd Floor 86-90 Paul Street London EC2A 4NE
support@cloudimg.co.uk
<https://cloudimg.co.uk>