

Rocky Linux 8 – WordPress

Version:	1.0.0
Created by:	cloudimg

Table of Contents

1.) Overview.....	1
2.) Access & Security.....	1
3.) System Requirements.....	2
4.) Connecting to the Instance.....	2
5.) On Startup.....	2
6.) Filesystem Configuration.....	3
7.) Server Components.....	3
8.) Scripts and Log Files.....	4
9.) Using System Components.....	4

1.) Overview

This document is provided as a user guide for the Rocky Linux 8 – WordPress product offering on the Azure Marketplace. Please reach out to support@cloudimg.co.uk if any issues are encountered following this user guide for the chosen product offering.

2.) Access & Security



Registered
Technology
Partner

cloudimg
(+44) 02045382725
3rd Floor 86-90 Paul Street London EC2A 4NE
support@cloudimg.co.uk
<https://cloudimg.co.uk>

Please update the security group of the target instance to allow the below ports and protocols for access and connectivity.

Protocol	Type	Port	Description
SSH	TCP	22	SSH connectivity
Custom TCP	TCP	3306	MySQL Database Listener Port for remote access
Custom TCP	TCP	80	WordPress site

3.) System Requirements

The minimum system requirements for the chosen product offering can be found below

Minimum CPU	Minimum RAM	Required Disk Space
1	1 GB	20 GB

4.) Connecting to the Instance

Once launched in the Azure Virtual Machines Service, please connect to the instance via an SSH client using the **azureuser** with the key pair associated at launch. Once connected as the **azureuser**, you will be able to **sudo** to the **root** user by issuing the below command.

Switch to the root user

```
sudo su -
```

5.) On Startup

An OS package update script has been configured to run on boot to ensure the image is fully up to date at first use. You can disable this feature by removing the script from `/stage/scripts/` and deleting the entry in crontab for the root user.

Disable the OS update script from running on reboot

```
rm -f /stage/scripts/initial_boot_update.sh
crontab -e
#DELETE THE BELOW LINE. SAVE AND EXIT THE FILE.
@reboot /stage/scripts/initial_boot_update.sh
```



Registered
Technology
Partner

cloudimg
(+44) 02045382725
3rd Floor 86-90 Paul Street London EC2A 4NE
support@cloudimg.co.uk
<https://cloudimg.co.uk>

6.) Filesystem Configuration

Please see below for a screenshot of the server disk configuration and specific mount point mappings for software locations.

Filesystem	Size	Used	Avail	Use%	Mounted on
devtmpfs	464M	0	464M	0%	/dev
tmpfs	481M	0	481M	0%	/dev/shm
tmpfs	481M	6.5M	475M	2%	/run
tmpfs	481M	0	481M	0%	/sys/fs/cgroup
/dev/xvda2	38G	3.1G	33G	9%	/
/dev/xvdf	9.8G	223M	9.1G	3%	/var/lib/mysql
/dev/xvda1	2.0G	184M	1.7G	11%	/boot
tmpfs	97M	0	97M	0%	/run/user/1002
/dev/xvdg	9.8G	104M	9.2G	2%	/var/www/html

Mount Point	Description
/boot	Operating System Kernel files
/var/lib/mysql	MySQL data directory
/var/www/html	WordPress site root

7.) Server Components

Please see below for a list of installed server components and their respective installation paths. The below versions are subject to change on initial boot based on the initial_boot_update.sh script finding new versions of the software in the systems package repositories.

Component	Version	Software Home
Cloud-Init	22.2	/etc/cloud
MySQL 8	8.0.29	/etc/my.cnf
Apache	2.4.37	/etc/httpd
PHP	8.0.21	/etc/php.ini
WordPress	6.0.1	/var/www/html/



Registered
Technology
Partner

cloudimg
(+44) 02045382725
3rd Floor 86-90 Paul Street London EC2A 4NE
support@cloudimg.co.uk
<https://cloudimg.co.uk>

Azure CLI	2.53.1	/lib64/az
-----------	--------	-----------

8.) Scripts and Log Files

The below table provides a breakdown of any scripts & log files created to enhance the useability of the chosen offering.

Script/Log	Path	Description
Initial_boot_update.sh	/stage/scripts	Update the Operating System with the latest updates available.
Initial_boot_update.log	/stage/scripts	Provides output for initial_boot_update.sh
mysql_root_password.log	/stage/scripts	MySQL root database password file
mysql_wordpress_password.log	/stage/scripts	Wordpress database password file

9.) Using System Components

Instructions can be found below for using each component of the server build mentioned in section 7 of this user guide document.

Azure CLI

Using Azure CLI – as any OS user.

```
az
```

Cloud-Init

Edit the /etc/cloud/cloud.cfg file to reflect your desired configuration. A link to the cloud-init official documentation can be found below for referencing best practise for your use case.

<https://cloudinit.readthedocs.io/en/latest/>

```
vi /etc/cloud/cloud.cfg
```



Registered
Technology
Partner

cloudimg
(+44) 02045382725
3rd Floor 86-90 Paul Street London EC2A 4NE
support@cloudimg.co.uk
<https://cloudimg.co.uk>

MySQL 8

The MySQL Database service has been configured to start on boot, please use the below commands to start, stop and check the status of the service.

```
#Check the MySQL service is running
service mysqld status

#Stop the MySQL service
service mysqld stop

#Start the MySQL service
service mysqld start
```

You can access the mysql database server as the root user by referring to the instructions in the /stage/scripts/mysql_root_password.log file. The root database user has been disabled for remote login as per best practise and therefore only a local login from the server command line will be allowed for the root user.

```
mysql -u root -p

#Enter the randomly generated password found in the /stage/scripts/mysql_root_password.log
file
```

Apache HTTP Server

The Apache HTTP Server has been configured to start on boot, please use the below commands to start, stop and check the status of the service.

```
#Check the HTTP Server is running
systemctl status httpd

#Stop the HTTP Server
systemctl stop httpd

#Start the HTTP Server
systemctl start httpd
```



Registered
Technology
Partner

cloudimg
(+44) 02045382725
3rd Floor 86-90 Paul Street London EC2A 4NE
support@cloudimg.co.uk
<https://cloudimg.co.uk>

PHP

You can check the PHP version running on the server by issuing the below command

```
php -v
```


WordPress

The WordPress connectivity details have been preconfigured in the `/var/www/html/wp-config.php` file. For reference of the values used, review the `/stage/scripts/mysql_wordpress_password.log` file for the WordPress MySQL database credentials.

Follow the below steps for accessing the WordPress Front End.

The Apache HTTP server has been configured to start on server boot and therefore WordPress will be accessible from initial launch. Navigate to the below URL exchanging the values between `<>` to match that of your instance.

`<PUBLIC/PRIVATEIP>/wp-admin`




Choose the preferred language
Click Continue



Registered
Technology
Partner


cloudimg
(+44) 02045382725
3rd Floor 86-90 Paul Street London EC2A 4NE
support@cloudimg.co.uk
<https://cloudimg.co.uk>



Enter the required values for your own use case. The values above are shown as examples only.

NOTE: Make note of the password used in the above field as it will be needed to log into WordPress in the next step.

Click Install WordPress




Click Log In




Registered
Technology
Partner

cloudimg
(+44) 02045382725
3rd Floor 86-90 Paul Street London EC2A 4NE
support@cloudimg.co.uk
https://cloudimg.co.uk



Enter the credentials created in the above step
Click Log In



Once successfully logged in, WordPress is available for use.



Registered
Technology
Partner

cloudimg
(+44) 02045382725
3rd Floor 86-90 Paul Street London EC2A 4NE
support@cloudimg.co.uk
<https://cloudimg.co.uk>